

Nematode Management Turfgrass

Table 1. Recommended nematicides, rates, and restrictions for managing nematodes in turfgrasses.

Time of Application	Nematicide ¹	Rate ²	Remarks
Pre-plant	Basamid G	302-446 lb	Mechanically incorporate to a depth of 6 inches. Follow label and observe temperature dependent waiting interval before planting.
	Dominus	10-40 gal	Waiting interval of 10-14 days before planting.
Post-plant	Multiguard Protect	8 gal (initially) 5.5-8 gal (for maintenance)	After initial treatment, apply maintenance rates at 14- to 28-day intervals. Irrigate to a depth of 6 inches. Can be applied up to 6 times per year.
	Indemnify	8.5-17 fl oz	Apply in 87-218 gallons of water per acre.
	Nortica	30-100 lb	Apply every 3 months as necessary and irrigate to a depth of 4 inches.
	Nortica 10 WP	35-50 lb	
	Telone II	5-10 gal	Use on established turf for sod farms. Not for golf greens.
	Divanem	3.125-6.25 fl oz	Apply at this rate on a 14-21-day interval.
		6.25-12.2 fl oz	Apply at this rate on a 21-28-day interval.
Quali-Pro Total	16-24 fl oz	Apply at this rate on a 14-21-day interval.	
	24-57 fl oz	Apply at this rate on a 21-28-day interval.	

¹Reference to commercial or trade names is made with the understanding that no discrimination or endorsement of a particular product is implied by LSU or the LSU AgCenter.

²Rates are the amount of formulation (product) per acre unless otherwise indicated.

The nematode section for turfgrass was revised October 2022 by T. Watson.