

Nematode Management Turfgrass

Table 1. Recommended nematicides, rates and restrictions for managing nematodes in turfgrasses.

Time of Application	Nematicide ¹	Rate ²	Remarks
Pre-plant	Basamid G	11-13 oz/100 sq. feet	Follow label and observe waiting interval before planting.
	Dominus	10-40 gal/A	Waiting interval of 10-14 days before planting.
Postplant	Multiguard Protect	8 gal (initially) 5.5-8 gal (for maintenance)	After initial treatment, apply maintenance rates at 14- to 28-day intervals. Irrigate to a depth of 6 inches. Can be applied up to 6 applications.
	Idemnify	0.195-0.39 oz/1,000 sq ft	Apply in 2-5 gallons of water.
	Nortica Nortica 10 WP	0.7-2.3 lbs/1,000 sq ft 0.8-1.15 lbs/1,000 sq ft	Apply every 3 months as necessary and irrigate to 4-inch depth.
	Telone II	5-10 gal	Use on established turf for sod farms. Not for golf greens.
	Divanem	3.125-6.25 fl oz/A 6.25-12.2 fl oz/A	Apply at this rate on a 14-21-day interval. Apply at this rate on a 21-28-day interval.
	Nimitz Pro G	60-120 lb/A	Incorporate by watering with at least 0.5 inch of water.

¹Reference to commercial or trade names is made with the understanding that no discrimination or endorsement of a particular product is implied by LSU or the LSU AgCenter.

²Rates are the amount of formulation (product) per acre unless otherwise indicated.

The nematode sections were revised October 2019 by Dr. C. Overstreet.